

Migration Tasks

If you have an instance of your CardioLog database already configured on a specific server, you can transfer the database and application to a new server when needed. This page describes the process for most configurations.

Contents

- [How to Migrate the CardioLog Database](#)
- [How to Migrate the CardioLog Application](#)
- [How to Configure CardioLog When Migrating a SharePoint Farm](#)
 - [Configure the SharePoint Farm Tree Structure](#)
 - [Configure Event Collection](#)

How to Migrate the CardioLog Database

To migrate the CardioLog database to another server, follow these steps:

1. Verify that there is a full backup of the CardioLog database on a separate drive.
2. Stop the CardioLog windows services including CardioLog Diagnostics Service and CardioLog Scheduling Service on the CardioLog application server.
3. Stop IIS on the CardioLog application server to stop data collection and HTTP requests to the CardioLog application during the move.
4. [Detach the CardioLog database](#) from the origin server.
5. Copy the database files (data + log) to the destination server.
6. [Attach the CardioLog database](#) to the destination server.
7. Edit the following CardioLog registry key accordingly:

- 32-bit machine - HKEY_LOCAL_MACHINE\SOFTWARE\Intlock\CardioLog
- 64-bit machine - HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intlock\CardioLog

"DATABASEINSTANCE"="[database server name]"

[database server name] - Confirm that the database server name is the server that hosts the CardioLog database.

8. Edit the database connection string in the following configuration files. The files should be located in the CardioLog Installation Folder.

The default path is *C:\Program Files\Intlock\CardioLog*:

- [CardioLog Installation Folder]\CardioLog\Web.config
- [CardioLog Installation Folder]\CardioLogAPI\Web.config
- [CardioLog Installation Folder]\CardioLogMonitoringServices\CardioLog.System.Monitoring.Services.exe.config
- [CardioLog Installation Folder]\CardioLogScheduleServices\CardioLog.Services.exe.config
- [CardioLog Installation Folder]\EventCollector\Web.config
- [CardioLog Installation Folder]\VisitorSegments\Web.config
- [CardioLog Installation Folder]\ADTree\Web.config
- [CardioLog Installation Folder]\SP2007Tree\Web.config
- [CardioLog Installation Folder]\SP2010Tree\Web.config
- [CardioLog Installation Folder]\SP2013Tree\Web.config
- [CardioLog Installation Folder]\SPTree\Web.config
- [CardioLog Installation Folder]\VoiceOfCustomer\Web.config
- [CardioLog Installation Folder]\Optimization\Web.config
- [CardioLog Installation Folder]\Redirect\Web.config
- [CardioLog Installation Folder]\WebsiteTree\Web.config

```
<add key="connStr" value="Integrated Security=SSPI;Persist Security Info=False;Initial Catalog=CardioLog;Data Source=[database server name]" />
```

[database server name] - Edit the database server name to match the new server that now hosts the CardioLog database.

9. Edit the database connection string in the configuration file located in the CardioLog Installation Folder. The default path is *C:\Program Files\Intlock\CardioLog*

- [CardioLog Installation Folder]\CardioLog\Web.config

```

<add name="VoiceOfCustomerEntities" connectionString="metadata=res://*;provider=System.Data.SqlClient;provider
connection string=&quot;Integrated Security=SSPI;Persist Security Info=False;Initial Catalog=CardioLog;Data Source=[data
base server name];MultipleActiveResultSets=True&quot;;" providerName="System.Data.EntityClient" />

<add name="CardioLogEntities" connectionString="metadata=res://*;provider=System.Data.SqlClient;provider connection
string=&quot;Integrated Security=SSPI;Persist Security Info=False;Initial Catalog=CardioLog;Data Source=[database
server name];MultipleActiveResultSets=True&quot;;" providerName="System.Data.EntityClient" />

```

[database server name] - Edit the database server name to match the new server that now hosts the CardioLog database.

10. Restart both CardioLog Windows services, CardioLog Diagnostics Service and CardioLog Scheduling Service, on the CardioLog application server.
11. Start IIS on the CardioLog application server.

How to Migrate the CardioLog Application

If you have not upgraded your product to the latest release yet, it is highly recommended to do so prior to migrating the CardioLog application. [Contact us](#) to receive the latest CardioLog installer. Find out more about the latest version by viewing [our site](#) and our [knowledge base](#). To find out what is current your product version, go to **Administration** in the navigation pane and click **Product License**.

To migrate the CardioLog application to another server, **using the existing database**, follow these steps:

1. Export the CardioLog registry key to a *.reg file:
 - 32-bit machine - HKEY_LOCAL_MACHINE\SOFTWARE\Intlock\CardioLog
 - 64-bit machine - HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intlock\CardioLog
2. Edit the CardioLog registry key (*.reg file):

```

"DATABASEINSTANCE"="[database server name]"

"TARGETDIR"="[CardioLog Installation Folder]"

```

[database server name] - The database server name that currently hosts the CardioLog database.

[CardioLog Installation Folder] - Edit the installation folder path to match the path that the CardioLog application will be installed on, on the new server.

3. Import the CardioLog registry key to the new server by copying the *.reg file to the new server and double clicking on it.
4. Disable both CardioLog windows services, CardioLog Diagnostics Service and CardioLog Scheduling Service, on the old CardioLog application server.
5. Run the CardioLog installer on the new server using the credentials of your [CardioLog service account](#). Follow the Installation Wizard steps.
6. [Contact us](#) to receive the required licenses for the new server and apply them using the License Admin tool (copy the Microsoft.Licensing.LicAdmin.exe tool from [CardioLog Installation Directory]\Setup Files\SLPS\ to [CardioLog Installation Folder]\CardioLogScheduleServices\ and execute it from there).
7. In the CardioLog database, edit the server name in the tab_management and tab_global_settings tables by executing the following SQL script (edit the old and new CardioLog server name):

```

Use CardioLog
GO

declare @oldName varchar(max) = 'CardioLog old machine name';
declare @newName varchar(max) = 'CardioLog new machine name';

---- 1. tab_management table
update tab_management
set
url = replace(url, @oldName, @newName),
serverName = @newName;

---- 2. Global settings
---- 2.1. CardioLog.Host
exec [dbo].[stp_global_settings_upsert] @Category = 'CardioLog', @Name = 'Host', @Value =
@newName, @ReplaceIfExists = 1;

---- 2.2. PdfExport.CardioLogPdfRoot
declare @value varchar(max) = (select Value from tab_global_settings where Category = 'PdfExport'
and Name = 'CardioLogPdfRoot');
if (@value is not null)
begin
set @value = replace(@value, @oldName, @newName);
update tab_global_settings set Value = @value where Category = 'PdfExport' and Name =
'CardioLogPdfRoot';
end

---- 3. tab_agent_params table

update tab_agent_params
set str1 = replace(str1, @oldName, @newName)
where AgentId in (2,4,6)

```

8. If you have implemented the [CardioLog Analytics SharePoint Feature](#) on your Web Front Ends (WFEs), edit all instances of the CardioLog server name (eg., `http://[CardioLog server name:port]/`) in the `/_layouts/CardioLogAgent/web.config` file, located on the SharePoint WFEs respectively:

`C:\Program Files\Common Files\Microsoft Shared\Web Server Extensions\14\TEMPLATE\LAYOUTS\CardioLogAgent\web.config`

Otherwise, edit the CardioLog Java Script tracking code embedded within a common Java Script file, located on your SharePoint WFEs. The code is located at the end of the file, between the comments: `//Intlock tracking code start` and `//Intlock tracking code end`

For MOSS 2007 only:

`C:\Program Files\Common Files\Microsoft Shared\Web Server Extensions\12\TEMPLATE\LAYOUTS\1033\core.js`

For SharePoint 2010 only:

`C:\Program Files\Common Files\Microsoft Shared\Web Server Extensions\14\TEMPLATE\LAYOUTS\1033\init.js`

For SharePoint 2013 only:

`C:\Program Files\Common Files\Microsoft Shared\Web Server Extensions\15\TEMPLATE\LAYOUTS\init.js`

For SharePoint 2016 only:

`C:\Program Files\Common Files\Microsoft Shared\Web Server Extensions\16\TEMPLATE\LAYOUTS\init.js`

9. If you have implemented the [CardioLog HTTP Module](#) for SharePoint on your Web Front Ends (WFEs), for each web site, modify the SharePoint Web.config file and edit the CardioLog server name (eg., `http://[CardioLog server name:port]/`) in the following key value:

`<add key="CardioLog.API.EventsServiceUrl" value="http://[CardioLog server:port]/CardioLogAPI/Events.asmx"/>`

How to Configure CardioLog When Migrating a SharePoint Farm

To configure the CardioLog application when migrating a SharePoint Farm from one location to another, follow these steps:

Configure the SharePoint Farm Tree Structure

1. In the **Administration** pane, click **System Configuration**, and then select **SharePoint Tree Adaptor**.

2. Select your SharePoint farm and edit the configuration settings accordingly (for more details see [this guide for SharePoint 2013 or lower](#) or [this guide for SharePoint 2016 or higher](#)).

Configure Event Collection

Install the CardioLog Analytics Tracking Agent feature on the migrated farm as detailed in [this guide](#).